Biomatik
Tel: (519) 489-7195, (800) 836-8089
Fax: (519) 231-0140, (877) 221-3515
Email: info@biomatik.com
http://www.biomatik.com

Peptide Handling (Solubility & Storage) Guideline

Version 8.1, Revision 2025-06-23

How to Dissolve a Peptide

Peptide solubility depends on the sequence, particularly the overall charge. While over 70% of peptides dissolve in water, almost all (about 99%) can be dissolved in DMSO. For specific solubility information, check the Certificate of Analysis provided with your peptide. If that information is not available, follow the step-by-step guideline below.

Step 1: Determine the Overall Charge of Your Peptide

Knowing your peptide's net charge at neutral pH will help you choose the best solvent. Here's how to calculate it:

- **Acidic residues (negatively charged):**
  - Aspartic acid (D), Glutamic acid (E), and the C-terminal free acid (COOH)
  - Each counts as –1
- **Basic residues (positively charged):**
  - Arginine (R), Lysine (K), Histidine (H), and the N-terminal free amine (NH_2)
  - Each counts as +1
- **Hydrophobic uncharged residues:**
  - Phenylalanine (F), Isoleucine (I), Leucine (L), Methionine (M), Valine (V), Tryptophan (W), Tyrosine (Y)
  - Each counts as 0
- **Other uncharged residues:**
  - Glycine (G), Alanine (A), Serine (S), Threonine (T), Cysteine (C), Asparagine (N), Glutamine (Q), Proline (P), acetyl, and amide
  - Each counts as 0

Example Calculations:

- **EFIRKRHDGASDL:** (+5) + (–4) = +1 → Basic peptide (use Method #1)
- **EHRLGAEKDEFIS:** (+4) + (–5) = –1 → Acidic peptide (use Method #2)
- **EFISEHRLDAGAK:** (+4) + (–4) = 0 → Neutral peptide (use Method #3)

Step 2: Choose the Proper Dissolution Method

Important: Always test solubility with a small aliquot (about 1 mg) before using your entire peptide batch.

Method #1 – For Basic Peptides (Overall Charge > 0)

1. **First,** try dissolving a small aliquot (1 mg) with sterile water.
   - You can use gentle sonication to help the peptide dissolve.
2. **If not soluble,** add a few drops of 10%–30% acetic acid and try again.
3. **If still not soluble,** add a small amount of trifluoroacetic acid (TFA, less than 50 µL) to fully dissolve the peptide.
   - After it dissolves, dilute with sterile water or buffer to your desired concentration.
   - **Note:** Do NOT use TFA if your peptide is intended for cell culture or biological assays, as TFA can be toxic to cells. In that case, use Method #3.

Biomatik
Tel: (519) 489-7195, (800) 836-8089
Fax: (519) 231-0140, (877) 221-3515
Email: info@biomatik.com
http://www.biomatik.com

Method #2 – For Acidic Peptides (Overall Charge < 0)

1. **First,** try dissolving a small aliquot (1 mg) with sterile water or 1X PBS (pH 7.4).
    - Sonication can be used to enhance solubility.
2. **If not soluble,** add a small amount of ammonium hydroxide (NH_4OH, less than 50 µL) or 10% ammonium bicarbonate (dropwise) to fully dissolve the peptide.
    - After it dissolves, dilute with sterile water or buffer to your desired concentration.
    - Make sure the final pH of your peptide solution is about 7. Adjust if needed.
    - **Note:** Do NOT use ammonium hydroxide for peptides containing cysteine, as it may promote disulfide bond formation. For those peptides, use Method #3.

Method #3 – For Neutral Peptides (Overall Charge = 0) or Highly Hydrophobic Peptides

1. **Try dissolving** a small aliquot (1 mg) with a small amount of DMSO.
2. **Once fully dissolved,** add the DMSO/peptide solution slowly (dropwise) to sterile water or buffer until you reach the desired concentration.
    - **For peptides containing cysteine:** Avoid DMSO, as it can oxidize cysteine side chains. Use DMF (dimethylformamide) or acetonitrile (ACN) instead.
    - **If aggregation occurs** (common with cysteine-rich peptides), add a small amount of 8M urea or 6M guanidine-HCl before dilution.

Special Notes on DMSO Use

- For most experiments, a final concentration of 5% DMSO (v/v) is recommended.
- For cell assays, keep DMSO at 0.5–1% or as low as possible. Some assays tolerate up to 5%, while others may only tolerate 0.5% or less.
- You can prepare a concentrated peptide stock in DMSO and dilute it with sterile water or buffer for your experiment.
- If solubilization fails, lyophilize (freeze-dry) the solution and try a different method.

How to Store a Peptide

- **Lyophilized peptides** are shipped at ambient temperature and are stable at room temperature for several weeks.
- **Long-term storage:** Store lyophilized peptides at –20°C or colder, away from bright light.
- **Peptides with methionine (M), cysteine (C), or tryptophan (W):**
    - These are prone to oxidation. Store in an oxygen-free atmosphere if possible.
    - Adding a reducing agent like dithiothreitol (DTT) can help prevent oxidation.
- **Moisture warning:**
    - Before opening a peptide vial, let it warm up to room temperature. This prevents moisture from condensing inside, which can decrease long-term stability.

Storing Peptide Solutions

- **Use solutions as soon as possible**—they are less stable than lyophilized powders.
- If you must store a peptide solution:
    - Aliquot and freeze at –20°C (preferably –80°C).
    - Avoid repeated freeze-thaw cycles.
    - Use a 0.2 µm filter to remove bacterial contamination if needed.

Biomatik
Tel: (519) 489-7195, (800) 836-8089
Fax: (519) 231-0140, (877) 221-3515
Email: info@biomatik.com
http://www.biomatik.com

- **Shelf life of solutions is limited, especially for peptides containing:**
  - Cysteine (C), methionine (M), tryptophan (W), asparagine (N), glutamine (Q), or N-terminal glutamic acid (E).
  - For example, cysteine-containing peptides oxidize easily, especially in basic conditions. Some residues (like proline) can racemize.
  - Peptide solutions are less stable at pH 8 or higher. **Keep stock solutions between pH 4–6** for best stability.